

Siargo User Application Quick Start Guide

1. Run SiargoUserApplication.exe from application executable folder.
2. There are 2 main options to choose at startup screen. (See Figure 1)
Click “Start Evaluation Test” button to run the product data acquisition test.
Click “History Viewer” button to view record data.




Figure 1

3. Click “Start Evaluation Test” button to start test. If user has working device connect to PC through right converter and set correct settings in App Setting (Step 8), the application may find the connected devices automatically. User may see the found device information in “Test Control” Panel. (See Figure 2)





Figure 2

4. There are 2 test modes for the data acquisition test. They are “Acquire Mode” and “Record Mode”. User may choose either one to run the test.
 - “Acquire Mode” runs the data acquisition test without data recording.
 - “Record Mode” runs the data acquisition test with data recording and the test file name and interval time can be user defined.
5. User may click “Start Data Acquisition” button to start test and “Stop” button to stop test. (See Figure 3)
 - User may choose “Serial Number” list to see the data update of all devices or any individual device.
 - User may choose “Data Name” list to see device parameter to show on chart.
 - User may choose “Viewer Mode (Table Mode, Chart Mode and Table & Graph Mode)” to see the testing progress.
 - User may click “Get/Set Param.” button  to show / hide panel to set parameter or offset for device(s).








Figure 3

6. User may view record data by click “History Viewer” button  on mainframe or click the button at startup screen. (See Figure 1)
7. User may click “Select file to load history data” button to choose record file. (See Figure 4, 5, 6)
 - User may choose “Data Name” list to see different parameter to show on graph.
 - User may choose “Viewer Mode (Table Mode, Graph Mode and Table & Graph Mode)” to view record data.

- User may click “InfoTable” button  to show or hide Information Table.
- User may click “Enable (Disable) Zooming” button  to Zoom in/out graph.
- User may click “Show (Hide) Cursor” button  to show graph data point.




Figure 4




Figure 5







Figure 6

8. User may click “Application Setting” button  to open application setting panel to Update dut & software settings in “App. Setting”. (See Figure 7)
 - User may choose the dut from “Product Type” and its according communication settings should be filled. User may also update the settings manually.
 - The “Addr.” Textbox is the dut address (only for I2c/Rs485) search range. The application may detect all searchable address to find the connected devices automatically.
 - User may click the “Save” button  to save the updated settings and click the “Refind Device” button  on Test Panel to see if the new settings effective or not. (See Figure 7)




Figure 7